

Creating QR Codes and Programming NFC Tags

Everything in the Rapid Cortex ecosystem — no third-party tools required

Browser

Create & download QR codes

RC Mobile App

Program NFC tags · Scan QR codes

RC Dashboard

View analytics & manage codes

Creating QR Codes

Browser — [app.rapidcortex.us](#)

1 Log into the RC web app

Go to [app.rapidcortex.us](#) in any browser.

2 Go to QR & NFC

Sidebar → select your agency → QR & NFC.

3 Tap “+ New QR / NFC Code”

Enter location name, zone, report type, vertical.

4 Click “Download PNG”

QR code image downloads to your computer.

5 Print and attach the QR code

Minimum 2” on wall signs.

Tip

QR codes work on every smartphone — no app needed.
Min 1.5” desk · 2” wall · 3” hallways

Programming NFC Tags

RC Mobile App — iOS & Android

1 Download the RC Mobile App

App Store or Google Play — search “Rapid Cortex”.

2 Sign in with your RC account

Same credentials as the web app.

3 Open QR & NFC

Select your agency, then open the location list.

4 Tap the location to program

e.g. “Main Lobby” or “Library 3rd Floor”.

5 Tap “Program NFC Tag”

App activates NFC and waits for a tag.

6 Hold the NTAG213 to the phone

Keep still — write takes about 2 seconds.

7 Tag programmed — test it

Tap the tag to confirm the report form opens.

Bonus

Booth signs: Trade show signs → Home or Demo.
Opens [www.rapidcortex.us](#) — not a report form.

App screens — NFC tag programming flow

Main Lobby

[app.rapidcortex.us/report/...](#)

Scan QR Code

Program NFC Tag

View Analytics

1 Location → Program NFC Tag

Program NFC Tag



iPhone: near top edge
Android: center back
Keep tag still...

2 Hold tag to phone

Tag programmed

Main Lobby tag is live.
Tap the tag to test it.

Write Another

3 Success — tag is live

Scan QR Code

QR code valid

4 Scan QR to verify

Rapid Cortex · [support@rapidcortex.us](#) · [app.rapidcortex.us](#)

Page 1 of 2

What You Need · Tips · Troubleshooting

What you need

- **RC admin account (web)**
app.rapidcortex.us · Agency Admin or higher · same account as the mobile app
- **RC Mobile App**
App Store or Google Play · sign in with your RC credentials
- **NTAG213 NFC sticker tags**
Search "NTAG213 NFC stickers" on Amazon · ~\$15–20 per 100 · round or square · white
- **Printer for QR codes**
Standard office printer · laser preferred · label paper or cardstock

Tips for best results

- **Create one code per physical location**
Never reuse URLs — you need per-location data to know where reports come from.
- **Label NFC tags before sticking**
Write the location name on the tag back with a marker before peeling.
- **Test before mounting**
Always tap the NFC tag and scan the QR code before attaching to a sign.
- **QR codes work on all phones**
NFC needs a newer phone. Put both QR and NFC on the same sign for full coverage.
- **Booth signs are not location codes**
Trade show signs → Home (www.rapidcortex.us) or Demo (/demo/).
Location tags open a report form.

Troubleshooting

NFC tag not detected

Turn NFC on (Settings → Connected devices → NFC). Move the tag slowly around the phone back to find the antenna.

Wrong page opens

Location tags open a report form. Booth signs: Trade show signs → Home or Demo, then Program NFC Tag. Location tags can be overwritten.

QR code won't scan

Check print size (min 1.5"). Clean smudges. Do not stretch or distort the PNG.

NFC works but QR doesn't

Re-download the QR PNG from the RC dashboard. Print larger or at higher quality.

App says "Write failed"

Enable NFC in phone settings. Hold the tag still — movement during write causes failures.

Quick reference

QR CODES (Browser)

1. app.rapidcortex.us → QR & NFC
2. + New QR / NFC Code → fill details
3. Download PNG
4. Print and mount

NFC TAGS (RC Mobile App)

1. Open RC app → QR & NFC
2. Tap location → Program NFC Tag
3. Hold NTAG213 tag to phone
4. Test · then mount the sign

TRADE SHOW (RC Mobile App)

1. Campus or Venue app → Trade show signs
2. Choose Home or Demo (not a location)
3. Save / print the QR · Program NFC Tag
4. Tap test → www.rapidcortex.us or /demo/